

Master File Task Screens

The following topics are covered:

- Master File Task Selection Menu
 - Add Master File Definition
 - Modify Master File Definition
 - Display Master File Definition
 - Delete Master File Definition
-

Master File Task Selection Menu

By either entering the MM direct command or selecting the "MM" option on the ETP Maintenance Utility Main Menu, the "Master File Definition Maintenance" screen appears.

| | | |
|------------------------------------|---|------------------------|
| 23:59:59 | ***** ENTIRE TRANSACTION PROPAGATOR ***** | 2000-12-24 |
| Master File Definition Maintenance | | |
| | | |
| AD | Add | master file definition |
| MO | Modify | master file definition |
| DI | Display | master file definition |
| DE | Delete | master file definition |
| | | |
| Command ==> | | |
| Enter-PF1--- | PF2--- | PF3--- |
| PF4--- | PF5--- | PF6--- |
| PF7--- | PF8--- | PF9--- |
| PF10--- | PF11--- | PF12--- |
| Help | Menu | Exit |
| Last | Flip | Tech |
| | | Canc |

The Master File Task Selection Menu

The master file tasks you select from this menu cause the screens described in the following section to appear.

Add Master File Definition

By either entering the Add MAster direct command or selecting the "AD" option on the Master File Definition Maintenance menu, the following screen appears.

| | | | | |
|--|---|--------|------------|------------|
| 23:59:59 | ***** ENTIRE TRANSACTION PROPAGATOR ***** | | | 2000-12-24 |
| Add master file definition | | | | |
| | DBID | FNR | Verify FDT | |
| Master file .. | _____ | _____ | Y (Y/N) | |
| Log file .. | _____ | _____ | Y (Y/N) | |
| ADABAS field name of distribution key ____ | | | | |
| NATURAL data format of distribution key ... ____ | | | | |
| Call user exit before replication N (Y/N) | | | | |
| Start program after ET N (Y/N) | | | | |
| Command ==> | | | | |
| Enter-PF1--- | PF2--- | PF3--- | PF4--- | PF5--- |
| PF6--- | PF7--- | PF8--- | PF9--- | PF10--- |
| PF11--- | PF12--- | | | |
| Help | Menu | Exit | Last | Save |
| | | Flip | | Tech |
| | | | | Canc |

The "Add Master File Definition" Screen

To define an ETP master file, enter the information in the fields, as described below.

Screen Field Description

| | |
|---|---|
| Master File DBID/FNR | Enter the database ID and file number of the Adabas file that becomes a master file. Specify "Y" (yes) under "Verify FDT" to verify the file's Field Definition Table (FDT); otherwise, enter "N" (no). You must make all entries; there are no defaults. |
| Log File FNR | Enter the file number of the Adabas file that is or will be the ETP log file. The log file must be on the same database as the master file. A single log file can be used for more than one master file. Specify "Y" (yes) under "Verify FDT" to verify the log file's Field Definition Table (FDT); otherwise, enter "N" (no). To ensure data consistency, the log file must be empty; otherwise, adding a master file is not allowed. |
| Adabas Field Name of Distribution Key | When any of the replicate files for this master file contain only a subset of master file records, one field must contain values or ranges of values that uniquely identify each replicate file's subset, and therefore the replicate file itself. Specify the two-letter Adabas field name of that identifying field here. The distribution key field cannot be a multiple-value (MU), a periodic group (PE) or field within a PE group, or a phonetic descriptor field; otherwise, an error occurs either during FDT verification, or when writing to the log file during operation. |
| Natural Data Format of Distribution Key | When you specify a field name for the Distribution Key field above, you must specify the field's Natural data type here (for example, A15 for a 15-byte alphanumeric field). Specifying the number of digits after the decimal point is not possible for numeric data types. |
| Call User Exit? | Specify "Y" (yes) if you want the WADUSER2 subprogram called after ETP checks the current transaction record's distribution key field, if any. ETP checks any distribution key to determine if a change to the master file must also be made to a specific replicate file. The default is "N" (no). |
| Start Program after ET? | Specify "Y" (yes) if you want to execute the program defined in the Modify System Profile task screen. The default is "N" (no). |

Modify Master File Definition

By either entering the MODify MAster direct command or selecting the "MO" option on the Master File Definition Maintenance menu, the "Modify Master File Definition" screen appears.

| | | | | |
|--|---|--------|------------|------------|
| 23:59:59 | ***** ENTIRE TRANSACTION PROPAGATOR ***** | | | 2000-12-24 |
| Modify master file definition | | | | |
| | DBID | FNR | Verify FDT | |
| Master file ..* | _____ | _____ | Y (Y/N) | |
| Log file ... | _____ | _____ | Y (Y/N) | |
| ADABAS field name of distribution key _ | | | | |
| NATURAL data format of distribution key ... _ | | | | |
| Call user exit before replication? _ (Y/N) | | | | |
| Start program after ET _ (Y/N) | | | | |
| Command ==> | | | | |
| Enter-PF1--- | PF2--- | PF3--- | PF4--- | PF5--- |
| PF6--- | PF7--- | PF8--- | PF9--- | PF10--- |
| PF11--- | PF12--- | | | |
| Help | Menu | Exit | Last | Save |
| | | | Flip | |
| | | | | Tech |
| | | | | Canc |

The "Modify Master File Definition" Screen

To change an existing master file's definition, enter the information in the fields as described below.

Screen Field Description

When the "Modify Master File Definition" screen is first displayed, you must either enter (or have already selected) a master file; otherwise, you cannot make entries in the rest of the fields. Once you have selected a master file and pressed Enter, you cannot change your selection unless you either exit and then re-enter the screen, or enter the SAVE command.

| | |
|---|---|
| Master File DBID/FNR | Enter the database ID and file number of the existing master file. If you enter a wild card in either the database ID or file number field, a window appears from which you can select a single master file definition for modification. |
| Log File FNR | Enter a new log file file number here. The log file must be on the same database as the master file. Note that if the current log file is not empty, a new log file cannot be defined. |
| Adabas Field Name of Distribution Key | When any of the replicate files for this master file contain only a subset of master file records, one field must contain values or ranges of values that uniquely identify each replicate file's subset, and therefore the replicate file itself. If the distribution key field is being changed, specify the two-letter Adabas field name of that field here. The distribution key field cannot be a multiple-value (MU), a periodic group (PE) or field within a PE group, or a phonetic descriptor field; otherwise, an error occurs either during FDT verification, or when writing to the log file during operation. Note that if any of the replicate files are still using the distribution key, it cannot be changed. |
| Natural Data Format of Distribution Key | When you specify a new field name for the Distribution Key field, you must specify the field's Natural data type here (for example, A15 for an alphanumeric field of 15 bytes). Specifying the number of digits after the decimal point is not possible for numeric data types. |
| Call User Exit? | Specify "Y" (yes) if you want the WADUSER2 subprogram called after ETP checks the current transaction record's distribution key field, if any. ETP checks any distribution key to determine if a change to the master file must also be made to a specific replicate file. The default is "N" (no). |
| Start Program after ET? | Specify "Y" (yes) if you want to execute the program defined in the Modify System Profile task screen. The default is "N" (no). |

Display Master File Definition

By either entering the DIisplay MAsTer direct command or selecting the "DI" option on the Master File Definition Maintenance menu, the "Display Master File Definition" screen appears.

| | | |
|--------------------------------|---|------------|
| 23:59:59 | ***** ENTIRE TRANSACTION PROPAGATOR ***** | 2000-12-24 |
| Display master file definition | | |
| Master file ..* | DBID | FNR |
| Printer name .. | (' ' = terminal) | |
| Command ==> | | |
| Enter-PF1--- | PF2--- | PF3--- |
| PF4--- | PF5--- | PF6--- |
| PF7--- | PF8--- | PF9--- |
| PF10--- | PF11--- | PF12--- |
| Help | Menu | Exit |
| Last | Flip | Tech |
| | | Canc |

The "Display Master File Definition" Screen

To display a master file's definition, enter the information in the fields as described below. To make changes to a master file's definition, enter the MODify MAsTer direct command on the command line at the bottom of the screen.

Screen Field Description

| | |
|----------------------|---|
| Master File DBID/FNR | Enter the database ID and file number of the master file you want displayed. If you enter a wild card in either the database ID or file number field, a window appears from which you can select one or more master file definitions for display. |
| Printer Name | To print out the selected master file definitions, enter a valid printer ID here. Leave this field empty to display the master file definition on your terminal. |

Delete Master File Definition

By either entering the DElete MAster direct command or selecting the "DE" option on the Master File Definition Maintenance menu, the "Delete Master File Definition" screen appears.

```

23:59:59          ***** ENTIRE TRANSACTION PROPAGATOR *****          2000-12-24
                        Delete master file definition

Delete master file ..*      DBID      FNR
                        _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  Last          Flip          Tech          Canc

```

The "Delete Master File Definition" Screen

Before you delete a master file definition, you must delete all related replicate files; the related log file must be empty.



Deleting a master file only removes the master file definition from the ETP administration file. The file and its contents still exist as a normal Adabas file in its original database and with its original file number.

To delete a master file's definition, enter the information in the fields as described below. To make changes to a master file's definition, enter the **MODIFY MASTER** direct command on the command line at the bottom of the current screen.

Screen Field Description

| | |
|--------------------------------|--|
| Delete Master File DBID/FNR | Enter the database ID and file number of the master file you want to delete. If you enter a wild card in either the database ID or file number field, a window appears from which you can select one or more master file definitions for deletion. |
|--------------------------------|--|

If you have requested the confirmation window using the Modify User Profile function, the confirmation window appears, asking you to confirm the deletion. If either of the following conditions exist:

- The log file has entries for the master file;
- A master file has one or more replicate files still defined.

- then a warning occurs, and the deletion request will be rejected.